

Quellen

<https://github.com/strukturag/spreed-webrtc/wiki/Ubuntu-Repository>

We maintain a repository for Ubuntu for easy installation of Spreed WebRTC.

```
$ sudo apt-add-repository ppa:strukturag/spreed-webrtc
$ sudo apt-get update
$ sudo apt-get install spreed-webrtc
```

After installation you should modify the configuration at `/etc/spreed/webrtc.conf` to your needs. At the very last you should generate your own secrets in the `[app]` section.

Logs can be found in `/var/log/spreed/webrtc/server.log`

The server listens on <http://127.0.0.1:8080/> per default.

Spreed.ME in Owncloud

Spreed.ME ownCloud app - This app can only be used in conjunction with a [Spreed WebRTC server](<https://github.com/strukturag/spreed-webrtc>).

You will not be able to use this app without such a server, but it's ****easy to set up**** one – The whole process only takes about 5-10 minutes – 2 minutes if you are fast ;).

- The latest version of this app can be found in the ownCloud app store or at [github.com/strukturag/owncloud-spreedme](<https://github.com/strukturag/owncloud-spreedme>)

Features - Securely communicate with your friends and family using rich audio-, video- and text chat right from your ownCloud installation - in your browser - Share presentations and other documents and save them to your ownCloud - Share your ownCloud presentations and other documents - Share your computer screen - Share YouTube videos - Much, much more :)

Preparations Before setting up this app (+ Spreed WebRTC) you need to ask yourself a few questions:

1. Do you want to run ownCloud and Spreed WebRTC on the same origin (i.e. on the same domain+port combination)?

(e.g. access ownCloud at `https://myowncloudserver.com:8443` and Spreed WebRTC at `https://myowncloudserver.com:8443/webrtc/`) ****-->**** Then use ****/webrtc/**** as your ****basePath**** for the next steps.

2. Do you want to run ownCloud and Spreed WebRTC on two different origins?

(e.g. access ownCloud at `https://myowncloudserver.com:8443` and Spreed

WebRTC at <https://webrtc.myowncloudserver.com:8080>) ****-->**** Then use an empty / no ****basePath**** for the next steps.

Note: We recommend using option **1.** as it's much easier to maintain. Also it seems that you can't use Screensharing in latest browsers when using option **2.**. We're working on a workaround so Screensharing also works with option **2.**, but for now option **1.** seems the way to go.

Installation / Setup of this app First off, here's a little encouragement: This list of steps might seem a bit long, but it's really easy to follow – we promise. You only have to set up this app once :)

1. Place this app in the **apps/** folder of your ownCloud installation. 2. Set up a Spreed WebRTC server and continue with the next step.

An easy-to-follow installation guideline can be found further below, see ****Installation / Setup of a Spreed WebRTC server****

3. You now should have a running Spreed WebRTC server. 4. This app requires you to change some settings in the ``server.conf`` of the Spreed WebRTC server (``webrtc.conf`` if you use the packaged version), namely:

```
1. In the **[http]** section:
  - **ONLY do this step if your basePath is not empty (see Preparations
  above):**
    Enable (= uncomment) **basePath** and set it to the basePath you
  determined above, e.g. **/webrtc/**
    (e.g. `basePath = /webrtc/`)
2. In the **[app]** section:
  - Enable **authorizeRoomJoin** and set it to **true**
    (`authorizeRoomJoin = true`)
  - Enable **extra** and set it to the full absolute path of the
**spreedme/extra** directory in your **apps** folder of your ownCloud
  installation
    (e.g. `extra = /absolute/path/to/owncloud/apps/spreedme/extra`)
  - Enable **plugin** and set it to **extra/static/owncloud.js**
    (`plugin = extra/static/owncloud.js`)
3. In the **[users]** section:
  - Enable **enabled** and set it to **true**
    (`enabled = true`)
  - Enable **mode** and set it to **sharedsecret**
    (`mode = sharedsecret`)
  - Enable **sharedsecret_secret** and set it to a random 64-character HEX
  string
    **Please note:** Do **NOT** use the string given below. Generate your
  own random 64-character HEX string!
    You can generate your own 64-character HEX string by running `xxd -ps
  -l 32 -c 32 /dev/random` or `openssl rand -hex 32`
    (e.g. `sharedsecret_secret =
  bb04fb058e2d7fd19c5bdaa129e7883195f73a9c49414a7eXXXXXXXXXXXXXXXXXX`)
4. Restart the Spreed WebRTC server for it to reload its configuration
```

5. Head over to the **apps/spreedme/config** folder in your ownCloud installation. Copy

`config.php.in` to `config.php` and adjust the constants as already done in `server.conf`:

```
1. Set `SPREED_WEBRTC_ORIGIN` to the origin of your WebRTC server
   (e.g. `const SPREED_WEBRTC_ORIGIN =
'https://webrtc.myowncloudserver.com:8443';`)
   **NOTE:** If you chose option **1.** in the Preparations step above, you
   can set `SPREED_WEBRTC_ORIGIN` to an empty string: `const
SPREED_WEBRTC_ORIGIN = ''`;
```

```
2. Set `SPREED_WEBRTC_BASEPATH` to the same basePath you already set in
the `server.conf` file
```

```
3. Set `SPREED_WEBRTC_SHAREDSECRET` to the same sharedsecret_secret you
already set in the `server.conf` file
```

6. Head over to the **apps/spreadme/extra/static/config** folder in your ownCloud installation. Copy `OwnCloudConfig.js.in` to `OwnCloudConfig.js` and adjust the constants as already done in `server.conf` and `config.php`:

```
1. Set `OWNCLOUD_ORIGIN` to the origin of your ownCloud server
   (e.g. `OWNCLOUD_ORIGIN: 'https://myowncloudserver.com:8443'`)
   **NOTE:** If you chose option **1.** in the Preparations step above, you
   can set `OWNCLOUD_ORIGIN` to an empty string: `OWNCLOUD_ORIGIN: ''`
```

7. Enable this ownCloud app by browsing to **/index.php/settings/apps** 8. **That's it.** You can now start communicating securely with your friends and family by opening **/index.php/apps/spreadme** of your ownCloud host in your browser.

For debugging, simply append `?debug` to that URL.

Limiting access to this app - By default, all users who can log in to your ownCloud installation can also use this app (and spread-webrtc) - If you want to limit access to this app (and spread-webrtc) only to a selected user-group, open ownCloud's user configuration site in your browser:
/index.php/settings/users - Create a new group there (e.g. "spread.me"). For sure you can also use an existing group (like "admin") - Now go to ownCloud's app configuration page
/index.php/settings/apps, find this app and check **Enable only for specific groups**. Then add all groups which should be able to use this app. - All users not in a group specified in the step above, will neither be able to use this app nor spread-webrtc.

Access by non-ownCloud users - If you want to use spread-webrtc with users who do not have an ownCloud account, you can enable the "Temporary Password" feature in `config/config.php` - This allows them to use spread-webrtc with a "Temporary Password", which admins **[1]** can generate by clicking on the key icon in the room bar of spread-webrtc or at
/index.php/apps/spreadme/admin/tp

- **[1]: Admins are either ownCloud admins or Spread.ME group admins. Create a group "Spread.ME" and add users as a group admin for that group to allow them to generate "Temporary Passwords"** ## Upgrading this app 1. Save the `config/config.php` and the `extra/static/config/OwnCloudConfig.js` file of your current spreadme apps directory 2. Download a newer version of this app 3. Replace the old folder with the new folder you just downloaded 4. Copy back the two files (step 1) to the appropriate folders 5. Consult CHANGELOG.md for changes you might need to follow ## Debugging this app - If you're having trouble getting this app and

Spread WebRTC server to run, simply open `/index.php/apps/spreedme/admin/debug` of your ownCloud host in your browser. It might contain information which can help to debug the issue. ## Installation / Setup of a Spread WebRTC server

1. Head over to [\[github.com/strukturag/spreed-webrtc\]](https://github.com/strukturag/spreed-webrtc)(<https://github.com/strukturag/spreed-webrtc>) and follow the instructions to install the Spread WebRTC server. For a packaged version (preferred) see [\[github.com/strukturag/spreed-webrtc/wiki/Ubuntu-Repository\]](https://github.com/strukturag/spreed-webrtc/wiki/Ubuntu-Repository)(<https://github.com/strukturag/spreed-webrtc/wiki/Ubuntu-Repository>) Please note: Your Spread WebRTC server has to be `_publicly_` accessible. You certainly want to adjust your `[nginx]`(<https://github.com/strukturag/spreed-webrtc/blob/master/doc/NGINX.txt>) / `[Apache]`(<https://github.com/strukturag/spreed-webrtc/blob/master/doc/APACHE.txt>) configuration accordingly. See ``./doc/example-config-nginx.txt`` for an example configuration on how to run ownCloud and spreed-webrtc on the same host.

2. Don't forget **to set your own secrets in the `[app]` section of spreed-webrtc's config file. At the very least you should change `sessionSecret` and `encryptionSecret`**.**

From:

<https://wiki.netzwissen.de/> - netzwissen.de Wiki

Permanent link:

<https://wiki.netzwissen.de/doku.php?id=nvidia&rev=1517327321>Last update: **05/03/2024 - 10:52**